
The release of ConfigMgr 1806 introduced the concept of high availability of the Site server by adding an additional primary site as passive node.

This post takes you through a step by step journey in configuring a highly available Site Server.

Here's a high-level architecture overview of the configuration which depicts a remote SQL AlwaysOn availability group hosting the ConfigMgr database and a remote shared Content Library.



Prerequisites and Recommendations-

## Remote SQL

As you plan to prepare your site for HA, the first thing to ensure is your SQL is also HA. This can be a SQL AlwaysOn or a SQL Cluster.

You can also start with a remote standalone SQL and later add it to an Availability Group. Refer this link for guidance.

**Remote Content Library** 

**Note** - Make sure the Distribution Point role is not installed locally on the primary site and needs to be removed before proceeding.

The Content Library also needs to be moved off the primary to a centralized location which can be a network/SAN share.

Moving Content Library –

- Create a Shared Folder
- Add the System/Computer Accounts of the both the Site Server (Active and Passive) with full permissions to this share.

Permissions for Share		×	Share Properties		
hare Permissions			General Sharing Security Previou	us Versions Cus	tomize
Group or user names:			Object name: C:\Share		
CM1 (CONTOSO\CM1s) CM2 (CONTOSO\CM2s)			Group or user names:		
R Everyone			CM2 (CONTOSO\CM2\$)		^
and Croyone			CM1 (CONTOSO'/CM1\$)		
			Administrator	h	~
			<		>
	Add	Remove	To change permissions, click Edt.		Edt
Permissions for CM1	Allow	Deny	Permissions for CM2	Alow	Deny
Full Control			Full control	~	^
Change			Modfy	Ĵ	
Read			Read & execute	2	
	_		List folder contents	ž	
			Read	ž	
			Wite	ž	~
			For special permissions or advanced click Advanced.	settings. j	Advanced

- Open ConfigMgr Console > Administration > Site Configuration > Sites
- Click Manage Content Library from the ribbon menu

) s• n	Add Site System Roles	Create Site System Server	Create Secondary Site	Retry Secondary Site Control Secondary Site Upgrade Site	<ul> <li>Show Install Statu</li> <li>Refresh</li> <li>Delete</li> </ul>	Manage Content Library	Configure Site Components •	Client Installation Settings • Settings
w 🕨	Site Configura I items	ation + Sites	5					
Searc	h							
lcon	Name	*	Туре	Server Name	State	Site Code	Parent Site Code	
1	P01 - Corp	orate Site	Primary site	CM1.contoso.lab	Site Active	P01		

• From the dialog, specify a folder inside the share (Not the root of the share) and click **Move**.

Selecting the root of the share will result in the following error - CContentDefinition::SyncFolder failed; 0x800700a1 SMS\_DISTRIBUTION\_MANAGER

Manage Content L	ibrary	×
Current Location:		
New Location:	\\sql1\Share\ContentLibrary	
	Move Cancel	

• The console will show the move in-progress. You can also refer to the DistMgr.log

Corporate Site						MoveContentLibrary	rary move progress to 36%. () Progress: Bytes: 919400771 of 2353889	255, Files: 8006 of 15126.
General Site Code: Server Name: Install Directory: Build Number: State:	P01 CM1.contoso.la C^Program File 8692 Site Active	b s\Microsoft Configuration	n Manager	Content Library Location: Status: Move Progress (%):	In progress 11	MoveContentLibrary Updating content libr MoveContentLibrary Updating content libr MoveContentLibrary	rary move progress to 39%. () Progress: Bytes: 967683070 of 235388 ary move progress to 41%. () Progress: Bytes: 1040307565 of 235388 rary move progress to 44%. () Progress: Bytes: 1137021459 of 235388 rary move progress to 48%.	89255, Files: 8675 of 15126.
		Corporate Site						
		General				Content Library		
		Site Code: Server Name: Install Directory: Build Number: State:	P01 CM1.contoso C:\Program F 8692 Site Active	ulab iles\Microsoft Configuration I	Manager	Location: Status: Move Progress (%):	\\sql1\Share\ContentLibrary Complete 100	

Remote SMS Provider

If the SMS provider is not already remote, install an additional SMS Provider [do not choose the passive site server] which is not local to the Primary Site.

Note – <u>ADK</u> is a prerequisite for SMS Provider

• Run the ConfigMgr setup and choose Modify SMS Provider configuration

System Center Configuration Manager Setup Wizard

te Maintenance
Site maintenance allows you to modify site configuration, and perform a site reset to reapply default file and registry permissions on this site server. Select the action that you want to perform.
<ul> <li>Reset site with no configuration changes</li> </ul>
O Modify SQL Server configuration
Modify SMS Provider configuration
Modify language configuration
O Upgrade the evaluation edition to a licensed edition. Enter the 25 character product key:

• Add the FQDN of the remote server [do not choose the passive site server] where you plan to install the SMS Provider and click **Next** 

	er Configuration Manager Setup Wizard SMS Providers	
SMS	S Providers are used by the Configuration Manager console to communicate with the site database.	
	Add a new SMS Provider Specify the server where the SMS Provider will be installed. SMS Provider (FQDN): Example: server1.contoso.com	
[	sql1.contoso.lab Note: The SMS Provider cannot be installed on a server that is configured for SQL Server clustering.	
5	SMS Provider server:	
	CM1.contoso.lab	
	< Previous Next > Cancel	

• Validate a successful install from the console.

Corporate Site Properties	×
Deployment Verification Security Sign General Wake On LAN Ports Server	Ing and Encryption Service Windows Ser Publishing Client Computer Communication Alerts
Comment:	
Type:	Primary site
Parent site:	None
Version:	5.00.8692.1000
Build number:	8692
Site server:	CM1.contoso.lab
Installation directory:	C:\Program Files\Microsoft Configuration Manager
SQL Server computer:	SQL1.contoso.lab
SMS Provider location:	CM1.CONTOSO.LAB SQL1.CONTOSO.LAB
	OK Cancel Apply

## Remote SUP

If the SUP role is not already remote, do plan to offload it from the Primary Site Server to a remote Server.

- Add additional SUP Server/s
- Remove SUP role from Primary Site and choose one of the remote SUP's as the new active source.

	ite System Role
This site system role is the sync source for new sync source for this site before remove	or all software update points in the site. Select a ring this role.
	~
SUP2 contoso net SUP3 contoso net	

Passive Site Server - Prerequisites

**Operating System:** 

The passive site server can run <u>any supported OS</u> and doesn't need to match the existing Primary Site Server OS.

This enables the scenario where you might want to move to a new OS for your Primary Site without performing an in-place upgrade or a backup/restore.

OS Features and ADK

• Download and Install ADK

Install the following features -

- Remote Differential Compression
- Remote Server Administration Tools > Windows Server Update Services Tools [WSUS sync will fail without this]


📥 Add Roles and Features Wiz	zard
Select features	
Before You Begin Installation Type	Select one or more features to install on the selected server.
Server Selection	
Server Roles	Remote Differential Compression
Features	Feature Administration Tools
Confirmation	<ul> <li>Role Administration Tools</li> </ul>
Results	D AD DS and AD LDS Tools
	Windows Server Update Services Tools
Results	<ul> <li>Hyper-V Management Tools</li> <li>Remote Desktop Services Tools</li> <li>Windows Server Update Services Tools</li> </ul>

## Permissions:

Add the System/Computer account of the Passive Site Server to the following locations -

- Content Library Share In case you missed from the previous step of moving the content library.
- Administrators Group of Active/Current Primary Site Server.
- Administrators Group of SQL Server (All nodes for SQL Clusters/AlwaysOn).
- SMS Admins group on all SMS Providers.
- System Management Container in AD.
- SysAdmin on SQL Server (All nodes for SQL AlwaysOn). Follow the instructions below -
  - Launch SQL Server Management Studio
    - Expand Security and select the machine account of the current Active Primary Site (Contoso\CM1\$)

Right click and choose Script Login as > CreateTo > New Query Editor Window



• Replace the computer account of the Active Primary Site to the Passive Primary Site and click **Execute**.



- Expand Databases > ConfigMgr DB CM\_P01 > Security
- Select the machine account of the current Active Primary Site (Contoso\CM1\$)
- Right click and choose Script Login as > CreateTo > New Query Editor Window



• Replace the computer account of the Active Primary Site to the Passive Primary Site and click **Execute**.

USE [CM_P01] GO		
CREATE USER [CON GO	TOSO\CM2\$] FOR LOGIN [CONTOSO\CM2\$	] WITH DEFAULT_SCHEMA=[dbo]
Messages		
Commands	completed successfully.	

Installing Passing Site Server

Adding the Passive Site Server system is straight forward.

• Create a new Site System Server from the Administration node.

<ul> <li>Site Configuration</li> </ul>	
Sites	
🔊 Servers and Site System Roles	Crasta Sita Surtam Sanuar
Citat Cations	Create Site System Server

Browse the desired Passive Primary Site Server FQDN and click Next

Create Site System Serve	r Wizard
neral xy	Select a server to use as a site system
tem Role Selection nmary gress npletion	Name (example: server1.corp.contoso.com):       CM2.contoso.lab       Ste code:   P01 - Corporate Ste
	Section: PDF Corporate site  Specify an FQDN for this site system for use on the Internet  Internet FQDN (example: internetary2.contoso.com)
	Require the site server to initiate connections to this site system     After the installation of the site system roles, the site server initiates all connections to the site system server by using the Site Syst     Installation Account.
	Site System Installation Account  Use the site server's computer account to install this site system  Use another account for installing this site system

• From the Role Selection page, choose Site server in passive mode and click Next

1 Create Site System Server Wizard

System Role Selec	ction
General Proxy System Role Selection	Specify roles for this server
Site Server In Passive Mor	Australia and an
Site Server in Passive Mot Summary Progress Completion	Available roles:         Application Catalog web service point         Application Catalog webste point         Certificate registration point         Cloud management gateway connection point         Data Warehouse service point         Badpoint Protection point         Enrollment point         Failback status point         Reporting services point         State server in passive mode         Software update point         State migration point
	You can manually promote the site server in passive mode to active mode.
	< Previous Next > Summary Cancel

- Choose your desired option to provide the Source files.
- Specify the Installation directory. [do not choose the root of the Program Files, it must be a directory inside and doesn't needs to be already present]

General	Specify the location of the Configuration Manager installation source files and directory to	
Proxy	use	
System Role Selection		
Site Server In Passive Summary Progress	Mot The Configuration Manager installation and source files will be obtained from the following location to install a site server in passive mode.	
Completion	Copy installation source files over the network from the site server in active mode	
	O Use the source files at the following location on the site server in passive mode	
	Local path: Example: C\SourceFiles	
	O Use the source files at the following network location	
	UNC path: Example: \\Server1\SourceFiles	
	Browne -	
	Specify the installation folder for the new site server:	
	C/Program Files/Microsoft Configuration Manager	

• Click Next to complete and finish the wizard.

Create Site System Server	Waard	×	Create Site System Server W	card
General Progy System Role Selection Site Server In Passive Mor Sommary Progress Completion	The wizard will create a new site system server with the following settings Detail:		General Prony System Role Selection Site Server in Passive Mor Summary Progress Completein	The Create Site System Server Wizard completed successfull  Detain  Create all patients server with the following satings:     Order all patients     Concerns Site System Server     Success Site Cole     Order Site Servers     Success Site Cole     Success Si

• Validate the progress in the FailOverMgr.log

The Scheduler and Sender creates job to copy the files to the Passive Site Server. You can also check the ConfigMgrSetup.log on the root of the Passive Site Server.

Refer the Installation Workflow in this link.

• Validate the successful completion on the console. Both the Active and Passive Site Servers with status OK

Search	7						
lcon	Name	Тур	pe	Server Name	State	Site Code	Parent Site Co
1	P01 - Corporate Site	e Pr	imary site	CM1.contoso.lab	Site Active	P01	
Corp	oorate Site						
lcon	Server Name	Site Code	Mode	Status			
Ð	\\CM1.contoso.lab	P01	Active	OK			
				OK			

The following Registry Keys are created which reflects the Passive Site Server –

• HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\SMS\Identification

Value name:		
Site Servers		
Value data:		
1;CM1.contoso.lab;0;CM2.contoso.lab;		
	OK	Cancel

• HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\SMS\Site Failover

Value name:		
Active Site Server Fqdn		
Value data:		
1;CM1.contoso.lab;0;CM2.contoso.lab;		
	ОК	Cancel

**Troubleshooting Installation** 

If you experience issues while installation, let's say you missed a prerequisite and the installation failed, refer the below steps.

• The Console status shows the Passive Site Server as Installation failed. You will get the right click option to Retry Installation

v •	Site Configuration   Sites					
ites 1	items					
Search	h					
con	Name	Туре	Server Name	State	Site Code	Parent Site Code
11	P01 - Corporate Site	Primary site	CM1.contoso.lab	Site Active	P01	
Corp	porate Site					
	Server Name Site Code	Mode	Status			
Corp Icon	1 <b>^</b> 1	Mode	Status OK			

- The reason for the failure is available under Monitoring > Site Server Status
- Click on Show Status to view the reason of failure.

Saved Show Retry installation Ste Server Install	view      Site Server Status				
	Site Server Status 2 iter     Icon Site Code N     D01	letwork OS Path Role CM1 contoso lab Site	Name server	Mode Active Passive	Status OK Installation failed
Site Server Installation Status Site Server Installation Status Site Server Installation Status	taftus				×
	er in passive mode to the	site P01			Refresh
Detailed status of adding a site serve					
Detailed status of adding a site serve		Status	Last Update Time		
^		Status Failed Not started	Last Update Time 8/31/2018 10:06:53 AM		

Name	Status	Last Update Time	Description
Primary FQDN	Completed	8/31/2018 10:06:42 AM	Checks if the FQDN p
🕗 Domain membership	Completed	8/31/2018 10:06:42 AM	Verifies that the comp
🕗 Administrative share (Site system)	Completed	8/31/2018 10:06:42 AM	Verifies that the requir
🕑 Site Server FQDN Length	Completed	8/31/2018 10:06:42 AM	Checking Site Server
Disting Configuration Manager server components on sit	Completed	8/31/2018 10:06:42 AM	Checks if the target sit
🖉 SQL Server sysadmin rights	Completed	8/31/2018 10:06:53 AM	Verifies that the user a
Unsupported site server operating system version for Set	Completed	8/31/2018 10:06:53 AM	Starting with version 1
Free disk space on site server	Completed	8/31/2018 10:06:42 AM	Checks that the site s
Pending system restart	Completed	8/31/2018 10:06:42 AM	Checks if a system res
Microsoft Remote Differential Compression (RDC) library r	Failed	8/31/2018 10:06:42 AM	Verifies that the Micro
Windows Deployment Tools installed	Completed	8/31/2018 10:06:42 AM	Checks whether the V
Windows Preinstallation Environment installed	Completed	8/31/2018 10:06:42 AM	Checks whether the V
🔮 User State Migration Tool (USMT) installed	Completed	8/31/2018 10:06:42 AM	Checks whether the U
Setup source files and directory access	Completed	8/31/2018 10:06:42 AM	Verifies if the machine
٢			>

Not started

Not started

[Completed]:Checks if the FQDN provided for the site system uses the primary DNS hostname for the computer.

Post Installation

Promotion

• Once you resolve the issue, click Retry Installation.

## Console

The ConfigMgr console is not installed as a part of the Passive Site Server installation and needs to be manually installed.

• Go to Installation directory > Tools > ConsoleSetup folder to initiate the installation.

Quick access		Name	Date m	odified	Туре	Size	
		🛃 AdminConsole	8/8/20	18 1:00 AM	Windows Installer	66,728 KB	
Desktop	*	Sector ConsoleSetup	7/14/20	018 10:50 PM	Application	604 KB	
Downloads	*	ReportViewer	2/25/20	018 1:46 AM	Application	4,646 KB	
Documents	*		😸 Configuration Mana	ger Console S	etup		×
Pictures	*		Please Wait				
This PC			Setup is configuring yo	our system.			
Network			Calling InstallUtil.exe				
<ul> <li>Network</li> </ul>			Calling InstallUtil.exe				
Network			Caling InstallUtil.exe				
Network			Calling InstallUtil.exe				

• Connect to the Passive Primary Site Server

Promote Passive Site Server - Planned

Its now time to test the Passive Site Server by promoting it as Active.

- Console > Administration > Site Configuration > Sites > Nodes Tab
- Select Passive Site Server > Right click and choose Promote to Active and confirm.

Corp	orate Site				nfiguration Manager		$\times$
con P	Server Name \\CM1.conto \\CM2.conto	Mode Active Passive	Status OK OK	Promote to active	This action wi active mode. Do you want t		
						Yes No	

• Note the change in Status from OK to **Promoting** (Passive to Active) and **Installing** for the Active to Passive site.

			¥	
lcon	Server Name	Site Code	Mode	Status
Ø	\\CM1.conto	P01	Passive	Installing
<b>I</b>	\\CM2.conto	P01	Active	Promoting

Subsequent failover will only change to Promoting for the Passive Site as it doesn't need to install any components

ł

Corp	Corporate Site						
lcon	Server Name	Site Code	Mode	Status			
	\\CM1.conto	P01	Active	Promoting			
	\\CM2.conto	P01	Passive	OK			

- Review the FailOverMgr.log on both the nodes.
- The Mode (Active/Passive) switches between the two Site Servers and Status to **OK**.

Corp	orate Site			
lcon	Server Name	Site Code	Mode	Status
P	\\CM1.conto	P01	Passive	OK
<b>O</b>	\\CM2.conto	P01	Active	OK

• The Primary Site Server name changes to the Passive Site Server which we just promoted to Active.

ninistration	< Sites 1	items							
Overview	Search	h							
Updates and Servicing	lcon	Name	Type	Server Name	State	Site Code	Parent Site Code		
Hierarchy Configuration	18	P01 - Corporate Site	Primary site	CM2.contoso.lab	Site Active	P01			
Cloud Services									
Site Configuration									
Reg Sites									
Servers and Site System Roles	Con	porate Site							
Sclient Settings									
Security	Gene	General				C	Content Library		
Distribution Points	Sit	e Code:	P01				Location:	\\sql1\Share\ContentLibra	
Distribution Point Groups		rver Name:	CM2.contoso.lab				Status:	Complete	
Migration		Install Directory: C:\Program Files\Microsoft Configuration Manager Build Number: 8692				Move Progress (%):	100		
Management Insights		ate:	Site Active						

Here's a Flowchart - Promote site server (planned)


Promote Passive Site Server – Unplanned [30-minute delay]

This will be an actual disaster scenario where the Active Primary Site Server is offline, and you need to promote the Passive Site Server to Active. There is no automatic failover.

The steps are same as above to switch a Passive Site Server to Active via the ConfigMgr Console.

**Note** – There is a 30-minute wait before the Passive Site Server switches to Active mode. Refer the <u>Unplanned</u> <u>Workflow</u> snippet below. The time start when you click Promote Active and not since the server is actually offline which could be longer.

I had to restart the Site Server to fully initialize and act as an Active Site Server.



Limitations and Non-HA Site System Roles

- Refer the Site Server HA Limitations in <u>this link</u>.
- Certain Site System roles do not support high availability (example Service Connection Point), the option is to Uninstall and Reinstall the role on a new server. Refer this link for guidance on each role.
- When you have two primary sites(active/passive), it may get confusing when you are troubleshooting and looking at logs. Always check the time stamps to be sure.